

Enrolling a Device

1. Before you begin, make sure device is logged onto the **BroncoWiFi** network. Password is **gosantaclara**. Skip to step 2 if computer is on wired connection.
2. Turn on device to be registered.
3. On your computer, navigate to <https://dashboard:8443/enroll> Enter in your Novell username and password and agree to the acceptable use policy. Click **Submit**. (Note: Some browsers will give messages regarding faulty security certificates. These should be ignored)
4. An enrollment form will pop up, like the one below. Fill out the information needed, providing a MAC address and device type. **MAC address and device type are required.**



5. Fill out email address, mobile number, and carrier if you wish to be notified upon successful approval.
6. Click **Add this entry**.
7. The device status will now appear on the bottom section of the page.

Additional

Go to it.scu.edu for more information on wireless access, additional information on setting up email, configuring mobile devices, printing, and more.

Try using these following tags for more information. First download Barcode Scanner for your mobile phone, open the app, and scan the tags.

SCU Information Technology



Contact Student Services



SCU Library



Student Technology Services

Santa Clara University
500 El Camino Real
Santa Clara, CA 95053
(408) 554-5050
www.scu.edu/it

Santa Clara University

Enrolling a Console or Media Player for Campus Use

Student Technology Services




Revised April 23, 2013

Wii MAC Address

1. Click on the **Wii** icon in the lower left corner.
2. Select **Wii Options** on the following screen.



3. Click the right arrow to advance to the **Wii System Settings 2** page.
4. Select **Internet**.
5. Select **Console Information**. The MAC Address will then be displayed.




Xbox360 MAC

1. Scroll down (if necessary) to **My Xbox**.
2. Select the far right tab labeled **System**.
3. Select **Network Settings**. Then select **Configure Network**.
4. Under **Basic Settings**, check to make sure **IP Settings** is on **Automatic**.
5. Go right and select the **Additional Settings** tab.
6. Go down and select the second item **Advanced Settings**.
7. Toward the bottom of the screen, the **Wired MAC Address** should be present. This is what you need to register device.



PS3 MAC Address

1. Go to the main menu and select **Settings**.
2. Select **Network Settings**.
3. Select **Settings and Connection Status List**.
4. Scroll down and the MAC Address will be displayed.



Media MAC Address

As these device type differ greatly, you should consult the device's manual in order to determine the MAC Address. If you do not have the device's manual, go to the manufacturer's web-site for more information.

If you have a new device that is not recognized, bring the device and user manual to the IT Student Helpdesk for help with enrollment.